

Entrydesign

 This article is designated for administrators.

About


The Entrydesign module allows media owners and co-editors to modify the styling of a specific media page.

This module is designated for Kaltura MediaSpace and KAF applications.

Configure

Enable the Module

enabled - When enabled, the **Display** tab is added to the editing capabilities of the Edit Entry page. See the example below.



Choose Who Can Design Entries

entryDesignRole - Choose roles, i.e. unmoderatedAdmin, admin, or privateOnly, or specific users or groups that are allowed to design media pages.

Provide Player Options

players - Provide the users with different player options to use on the media page. If left blank, the site's default player is used.

Click **+Add "players"** to add players to the list of available players. Enter a player display name and player ID, then select an entry type from the drop-down menu.

Continue to add players as desired by clicking **+Add "players"**.

Select Player Behavior

showEmbedPlayerOption - Select the player behavior with the embed and default players. If the admin selects "User Selects", a button called **Set as Embed Player** displays next to the player selection.

- **Force Entrydesign Player in Embed Code** - If selected, the Entrydesign player will be used in the embed code of the Share tab. Players designated in the Embed module will be overridden.
- **Use Embed Module Players** (default) - If selected, the Embed player will be used in the embed code of the Share tab. Players designated in the Entrydesign module will be overridden.
- **User Selects** - If selected, in case a player is set for the corresponding entry type in the Entrydesign module, the owner/co-editor will see additional fields to select the "Entry Player" and a tickbox "Set as Embed Player". Players designated in the Embed module will be overridden.

The following example demonstrates players set for the Video and Webcast entry types.

players

Fill in the player ID and player display name you wish to allow the users to use in the entry page. If no Player ID is filled, the site's default player will be used.

1 **DELETE**

playerDisplayName

Video player

Player Display Name

playerId

48991433

Player ID

entryType

Video

Entry Type

2 **DELETE**

playerDisplayName

Webcast Live Player

Player Display Name

playerId

43898211

Player ID

entryType

Webcast/Live

Entry Type

+ Add "players"

The following example demonstrates the Display tab setting of a **video** entry type, hence the video player was added for selection (The Webcast Live Player was not added in this case).

Use the Display tab to change or modify an entry's display.

Entry player: Default player ▼

Default player
Video player


Set as Embed Player: ☐

Use the selected player when generating embed codes

Media Page Styling Features

allowedElements - Select which elements are displayed for the media owners to control. Media owners will be able to choose which of these elements to display or remove through the Edit Entry page. Options may include sidebar, entry properties, entry tabs, comments, header, header logo, and footer. For more information on each option, see [Customize the Media Entry Display - For Users](#).

In our example below, the Admin has chosen to provide users control of showing the sidebar, comments, and footer. The user has chosen to show all three elements on the page with the video (all three are checked).



The screenshot shows the Kaltura media player interface. At the top, there is a video player with a progress bar at 0:00 / 5:16. Below the player is a search bar and a 'Show transcript' link. The main navigation bar includes tabs: Details, Publish, Options, Collaboration, Thumbnails, Presenters, Downloads, Captions, Timeline, Replace Media, and Display (which is currently selected). Below the navigation bar, the 'Display' tab settings are shown. It includes a dropdown for 'Entry player' set to 'Default player', a 'Show elements' section with checkboxes for 'Sidebar', 'Comments', and 'Footer' (all three are checked), and a 'Background color' section with a color picker.

Use the Display tab to change or modify an entry's display.

Entry player: Default player ▼

Choose a player for this entry


Show elements: ☒ Sidebar ☒ Comments ☒ Footer

Choose what elements should show on the page with the video

Background color:

Choose the color of the entry page background

In our next example below, the Admin has chosen to provide users control of showing all available elements. The user has chosen to show sidebar, entry properties, entry tabs, and comments on the page with the video (those four are checked).



allowCSS - Set to **Yes** to allow the entry owner to use CSS to change the look and feel of the page. If enabled, this option displays to the user on the Edit Entry page as follows.

CSS: No file chosen
Upload a CSS file to customize the entry's page.

allowLogoChange - Set to **Yes** to allow the entry owner to set a new logo for KMS when viewing the entry. If enabled, this option displays to the user on the Edit Entry page as follows.

Different logo: No file chosen
Add a logo image file to show for this entry only. Default logo size is 325px wide X 41px high. Note: The width of the logo image affects the amount of space available for the Header menu.

showLastArchived - Set to **Yes** to allow live entry owners to change the default settings of showing a link to the last archived video on top of the live page.

Save

Save - Click **Save** to save your configuration settings.

[template("cat-subscribe")]